



Tutorial 1 – ARC EM9D AloT DK Environment Installation

Willie Tsai 2023/02/06





Install VirtualBox



1. Download the installation file

https://www.virtualbox.org/wiki/Downloads?fbclid=IwAR12O6-1e_Dg00CFt4xuChqjJSuGKQwgVZDZa3MI-I2QojYsEq9ILe3bWLQ



VirtualBox Download VirtualBox Here you will find links to VirtualBox binaries and its source code.

About

Screenshots

Downloads

Documentation

End-user docs

Technical docs

Contribute

Community

VirtualBox binaries

By downloading, you agree to the terms and conditions of the respective license.

If you're looking for the latest VirtualBox 6.0 packages, see VirtualBox 6.0 builds. Please also use version 6.0 if you need


If you're looking for the latest VirtualBox 5.2 packages, see VirtualBox 5.2 builds. Please also use version 5.2 if you still

VirtualBox 6.1.18 platform packages


⇒Windows hosts

- □→US X nosts
- Linux distributions
- ➡Solaris hosts
- ➡Solaris 11 IPS hosts


The binaries are released under the terms of the GPL version 2.



3. Click "Next" and "Install"



4. Click "Finish" and you will see the UI of VM Virtual







Install Cygwin



1. Download the installation file https://cygwin.com/install.html





Get that Linux feeling - on Windows


Installing and Updating Cygwin Packages


Installing and Updating Cygwin for 64-bit versions of Windows


Run setup-x86_64.exe any time you want to update or install a Cygwin package for 64-bit windows. The signature for setup-x86_64.exe can be














5. Choose "Full" in "View"




- 6. Install module:
 - 1. Search "git", "xxd", "make", "unzip" and "curl"
 - 2. Click and select the latest version and click the checkbox
 - 3. After configure all module in step1, click "Next"




7. Click "Next" and start to install





8. Click "finish"







Install Teraterm



1. Download the installation file https://ttssh2.osdn.jp/index.html.en

Tera Term Home Page

[Project page] [License] [Download] [Document] [Snapshot] [SourceCode] [Users ML] [Commit ML] [Development]



TeraTerm Project


TeraTerm Project would have been developed terminal emulator "Tera Term" and SSH module "TTSSH". This software is open source softwar in Project Page on OSDN.

Download

Latest version is available from OSDN <u>download page</u>. Current latest release is <u>4.105</u>.

If you can get latest development version, the source code is available from <u>SVN repository</u>. And <u>snapshot</u> is here. Here is the <u>Old release</u>, however we recommend using the latest release as possible.


2. Download the last version




3. Accept the agreement after reading it and press next




4. Press next English is recommended



5. Keep pressing next and install



6. Press finish








Install VScode




Download the installation file

https://code.visualstudio.com/download




Download Visual Studio Code


Free and built on open source. Integrated Git, debugging and extensions.




2. Click "I accept the agreement" and "Next"




3. Click "Create a desktop icon" and "Next"




4. Click "Install"



5. Click "Finish"



6. Open VScode







Install ARC GNU ToolChain




1. Download the installation file and select version 2019.09


Please download the version without rc label

https://github.com/foss-for-synopsys-dwc-arc-processors/toolchain/releases/tag/arc-2019.09-release


	Linux x86_64	Windows x86_64	Linux ARC HS	macOS x86_64
Baremetal	Little endian \ Big endian			Little endian \ Big endian
Linux/uClibc ARC700	Little endian \ Big endian			
Linux/uClibc ARC HS	Little endian \ Big endian		Little endian	
Linux/glibc ARC HS	Little endian \ Big endian			
IDE	Download	Download		Download

2. Double click the installation file and click "I Agree"







4. Click "Install"



5. Start to install...



6. Click "Close" and complete the installation



ARC GNU ToolChain Installation

1. Download the installation file and select version 2019.09

Please download the version without rc label

https://github.com/foss-for-synopsys-dwc-arc-processors/toolchain/releases/tag/arc-2019.09-release

	Linux x86_64	Windows x86_64	Linux ARC HS	macOS x86_64
Baremetal	Little endian \ Big endian			Little endian \ Big endian
Linux/uClibc ARC700	Little endian \ Big endian			
Linux/uClibc ARC HS	Little endian \ Big endian		Little endian	
Linux/glibc ARC HS	Little endian \ Big endian			
IDE	Download	Download		Download








If the USB serial port is not shown in Ports (COM & LPT):

- 1. Download VCP driver: https://ftdichip.com/drivers/vcp-drivers/
 Select setup executable
- 2. Unzip and execute the file

		Processor Architecture							
Operating System	Release Date	X86 (32- Bit)	X64 (64- Bit)	PPC	ARM	MIPSII	MIPSIV	SH4	Comments
Windows (Desktop)*	2021-07- 15	2.12.36.4	2.12.36.4	-	2.12.36.4A****	-	-	-	WHQL Certified. Includes VCP and D2XX. Available as a setup executable Please read the Release Notes and Installation Guides.

- 3. Click "Extract"
- 4. After finish-ing this process, click "Next" to install





5. Finish









If the USB serial port is not shown in Ports (COM & LPT):

1. Download VCP driver:

https://www.silabs.com/developers/usb-to-uart-bridge-vcp-drivers
Select CP210x VCP Windows version

2. Unzip the downloaded file (CP210x_VCP_Windows)
Software • 10


CP210x Universal Windows Driver	v11.1.0 3/22/2022
CP210x VCP Mac OSX Driver	v6.0.2 10/27/2021
CP210x Windows Drivers	v6.7.6 9/4/2020
CP210x Windows Drivers with Serial Enumerator	v6.7.6 9/4/2020
CP210x_5x_AppNote_Archive	9/4/2020

Show 5 more Software

- 3. Execute "CP210xVCPInstaller_x64.exe" or "CP210xVCPInstaller_x86.exe" dependence on your PC
- 4. Click "Next"



5. Finish







Appendix-1: Metaware Install (Option) (For user in Taiwan)



•台灣學界人員可向TSRI申請MetaWare使用權限,申請流程可至TSRI網站,

設計服務 > 軟體申請須知 進行查詢。

https://www.tsri.org.tw/main.jsp

- 請指導教授先完成申請TSRI會員, 接著即可申請要使用之軟體, 並且登錄欲要用該軟體之實驗室電腦IP。
- 指導教授為TSRI會員後,學生可點選 登入會員,接著選擇註冊帳號,填寫完 相關資訊,並等待相關程序處理完畢。



- 進入TSRI 官網 https://www.tsri.org.tw/main.jsp
- ●點選設計服務->軟體資訊/下載



•點選軟體申請,跳至會員登入頁面,並完成登入動作

軟體簡介

軟體簡介

名稱: MetaWare Development Toolkit

簡介:

軟體功能:

為因應國内學術界對ARC嵌入式軟體開發工具的需求,TSRI引進新思(Synopsys)公司的DesignWare MetaWare Toolkit軟體開發工具,開

计纵段作用名类由注法口



功能權限錯誤

您需要先登入才能使用此功能。

其他問題可以先參考申請須知。

聯絡我們

新竹辦公室: 30078 新竹市科學園區展業一路26號

台南-成大奇美樓: 70101台南市大學路1號成功大學自強校區奇美樓7樓

最佳瀏覽解析度為1366*768以上


軟體資訊



IP登録

聯絡窗口

- Ctrl+f 搜尋Meta
- 點選MetaWare Development Toolkit



• 點選軟體取得



軟體簡介

名稱: MetaWare Development Toolkit

簡介:

軟體功能:

為因應國內學術界對ARC嵌入式軟體開發工具的需求,TSRI引進新思(Synopsys)公司的DesignWare MetaWare Toolkit軟體開發工具,開放給學術界免費申請使用。

DesignWare MetaWare Toolkit可以針對ARC HS及ARC EM 平台進行相關的軟體開發、分析及除錯。

軟體內容:

- 1. 單一工具鏈支援所有ARC處理器(ARC 600, ARC 700, ARC EM and ARC HS)
- 2. 支援進階C++語法,包含Standard Template Library for ARC
- 3. OS Aware Debugger 可針對 MQX RTOS for ARC
- 4. 支援多核心除錯
- 5. Eclipse-based IDE

系統需求:

Windows 7/10, 64-bit

RHEL 6.6/6.7/6.8/7.1/7.3, 64-bit

1 GB of RAM

• 下載mwev

軟體簡介 軟體取得 審作範例 MetaWare Development Toolkit 軟體取得 2020.09 檔案名稱 檔案說明 檔案大小 下載連結 mwev_R-2020_09_win_install.exe MetaWare Development Toolkit for Windows 64位元版安裝檔 3,382,128,416 bytes 下載 Synopsys caffe 安裝檔 for Windows, install with mwev_R-2020_09_win_install.exe 2,317,838,362 bytes 下載 synopsys_caffe_v2020_09.exe MWDT 2020.09 linux 1of3.tgz MetaWare Development Toolkit for Linux Disk 1/3 866,315,860 bytes 下載 MWDT_2020.09_linux_2of3.tgz MetaWare Development Toolkit for Linux Disk 2/3 1,419,168,522 bytes 下載 MetaWare Development Toolkit for Linux Disk 3/3 MWDT 2020.09 linux 3of3.tgz 2,100,589,978 bytes 下載 mwev_R-2020_09_build_info.txt MetaWare Development Toolkit 軟體版本說明檔 359 bytes 下載

- 進入控制台->系統及安全性->系統->進階系統設定->
 - ->環境變數->系統變數新增

調整電腦設定



使用檔案歷程記錄來儲存檔案的備份副本 備份與還原 (Windows 7)



網路和網際網路

檢視網路狀態及工作



硬體和音效

檢視裝置和印表機 新增裝置



SYNOPSYS°

程式集





使用者帳戶 🛑 變更帳戶類型



外觀及個人化



時鐘和區域

變更日期、時間或數字格式




53


輕鬆存取

譲 Windows 建議設定 最佳化視覺顯示


檢視:









- 變數名稱:SNPSLMD_LICENSE_FILE
- 變數值:26585@lscic.cic.org.tw
- 輸入完成後按下確定




•確認新增成功,成功後重新啟動電腦




- •執行mwev_R_2020_09_win_install
- •接下來步驟都點選Next



• 勾選 I accept ...



• 如果License check失敗,請回到第五頁確認新增環境變數成功



• 點選Done完成安裝

